

**Segment Installation Procedures
Server COE Web Help (Software)
(Server COEWEBHelpSW)
Version 1.0.0.1 (HP-UX 10.20)**

September 29, 1997

Table of Contents

Preface	ii
1. Installation Procedures	1
1.1 Scope	1
1.1.1 Identification	1
1.1.2 System Overview	1
2. Referenced Documents	3
3. System Environment	5
3.1 System Requirements	5
3.1.1 Hardware Requirements	5
3.1.2 Operating System Requirements	5
3.1.3 Kernel Requirements	5
3.2 System and Site Preparations	5
3.2.1 System Configuration	5
3.2.2 Operation System Preparation	5
3.2.3 Tape/Disk Preparation	5
4. Installation Instructions	7
4.1 Media Booting Procedures	7
4.2 Installation Procedures for the ServerCOEWEBHelpSW Segment	7
4.2.1 De-Installation Procedures	7
4.3 Installation of Upgrades	7
4.4 Installation Verification	7
4.5 Initializing the Software	8
4.6 List of Changes and Enhancements	8
4.7 Important Considerations	8
5. Notes	9

Preface

The following conventions are used in this document:

Bold	Used for information that is typed, pressed, or selected in executables and instructions. For example, select connect to host .
<i>Italics</i>	Used for file names, directories, scripts, commands, user IDs, document names, and Bibliography references; and any unusual computerese the first time it is used in text.
<u>Underline</u>	Used for emphasis.
Arrows <>	Used to identify keys on the keyboard. For example <Return>.
“Quotation Marks”	Used to identify informal, computer-generated queries and reports, or coined names; and to clarify a term when it appears for the first time. For example “Data-Generation Report.”
Courier Font	Used to denote anything as it appears on the screen or command lines. For example <code>tar xvf dev/rmt/3mm</code> .
Capitalization	Used to identify keys, screen icons, screen buttons, field, and menu names.

1. Installation Procedures

1.1 Scope

The Installation Procedures (IP) outlined in this document pertain to the Server Common Operating Environment (COE) Web Help Software (ServerCOEWEBHelpSW) segment, Version 1.0.0.1 (V1.0.0.1). This segment is delivered for the Defense Information System (DII) for both Hewlett-Packard (HP)-based and Solaris-based platforms.

1.1.1 Identification

This section contains identification information for the ServerCOEWEBHelpSW segment:

Segment Name:	Server COE Web Help (Software)
Segment Type:	SOFTWARE
Prefix:	SWHSW
Home Directory:	/h/ServerCOEWEBHelpSW
Required License:	None
Version Number:	1.0.0.1
Platform:	HP (UNIX) Workstation/HP-UX 10.20

1.1.2 System Overview

This section contains system overview information for the ServerCOEWEBHelpSW segment:

Purpose:	The ServerCOEWEBHelpSW segment contains a sample software segment and application source and executable code which, along with the associated Server COE Web Help (Data) (ServerCOEWEBHelpDATA), demonstrates how a developer can integrate Web-based help documents into a mission application's operating environment.
Usage:	Developers may use the ServerCOEWEBHelpSW segment as an aid for developing and implementing server-based Web help documents.
References:	The <i>COE Web Help Developer's Guide</i> which has been delivered with the associated ServerCOEWEBHelpDATA segment. Users may also refer to the on-line version of this manual by installing and running the sample application contained in this segment, and selecting the COE Web Help menu item on the Help menu.

This page intentionally left blank.

2. Referenced Documents

The following documents are referenced in this Installation Procedures document:

COE Web Help Developer's Guide delivered with the ServerCOEWEBHelpDATA segment, V1.0.0.1.

This page intentionally left blank.

3. System Environment

3.1 System Requirements

3.1.1 Hardware Requirements

The following HP hardware is necessary to install the ServerCOEWEBHelpSW segment:

- C HP-UX 10.20
- C 55 KB of disk space
- C 16000 KB of memory

3.1.2 Operating System Requirements

The HP operating system must be at least HP-UX 10.20 to install the ServerCOEWEBHelpSW segment.

3.1.3 Kernel Requirements

The following DII COE Kernel is required to install the ServerCOEWEBHelpSW segment:

DII COE Kernel V3.2 for HP-UX 10.20 for the HP version of ServerCOEWEBHelpSW.

3.2 System and Site Preparations

3.2.1 System Configuration

None.

3.2.2 Operation System Preparation

None.

3.2.3 Tape/Disk Preparation

Rewind tape before beginning installation process.

This page intentionally left blank.

4. Installation Instructions

4.1 Media Booting Procedures

None.

4.2 Installation Procedures for the ServerCOEWEBHelpSW Segment

Use the following steps to install the ServerCOEWEBHelpSW segment:

- Step 1: Select **Server COE Web Help (Software)** from the COE Installer's Select Software to Install window and press the **INSTALL** button.
- Step 2: Enter the name of the web server machine that is hosting the Web Help files contained in the ServerCOEWEBHelpDATA segment at the following prompt:
- Enter the name of the Web server hosting help documents for this application.
- Step 3: Respond appropriately to any other COEInstaller prompts.

4.2.1 De-Installation Procedures

Use the following steps to de-install the ServerCOEWEBHelpSW segment:

- Step 1: Select **Server COE Web Help (Software)** from the COE Installer's Currently Installed Segments window and press the **DEINSTALL SOFTWARE** button.
- Step 2: Respond appropriately to any COEInstaller prompts.

4.3 Installation of Upgrades

None.

4.4 Installation Verification

To verify that this segment has been installed, verify the following:

- C The `/h/COE/Comp/WEBSv/lib/config/obj.conf` file on the web server hosting the Web Help files contained in the ServerCOEWEBHelpDATA segment was modified.

- C The associated ServerCOEWEBHelpDATA segment is installed.

Execute the following command from a command line:

```
/h/ServerCOEWEBHelpSW/bin/SWHSW_COEWEBSampleApp
```

When the COE Web Help Sample Application main window is displayed, select the **COE Web Help** menu item from the Help menu. The *COE Web Help Developer's Guide* should be displayed in the Netscape browser window that appears.

4.5 Initializing the Software

Not required.

4.6 List of Changes and Enhancements

Not applicable.

4.7 Important Considerations

None.

5. Notes

None.

This page intentionally left blank.